

RTI Limited Bandwidth Endpoint Discovery Plugin

Installation Guide

Version 6.0.0



© 2019 Real-Time Innovations, Inc.
All rights reserved.
Printed in U.S.A. First printing.
February 2019.

Trademarks

Real-Time Innovations, RTI, NDDS, RTI Data Distribution Service, Connex, Micro DDS, the RTI logo, IRTI and the phrase, “Your Systems. Working as one,” are registered trademarks, trademarks or service marks of Real-Time Innovations, Inc. All other trademarks belong to their respective owners.

Copy and Use Restrictions

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form (including electronic, mechanical, photocopy, and facsimile) without the prior written permission of Real-Time Innovations, Inc. The software described in this document is furnished under and subject to the RTI software license agreement. The software may be used or copied only under the terms of the license agreement.

This is an independent publication and is neither affiliated with, nor authorized, sponsored, or approved by, Microsoft Corporation.

The security features of this product include software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>).

Technical Support

Real-Time Innovations, Inc.

232 E. Java Drive

Sunnyvale, CA 94089

Phone: (408) 990-7444

Email: support@rti.com

Website: <https://support.rti.com/>

Contents

Chapter 1 Installing	1
Chapter 2 Paths Mentioned in Documentation	3

Chapter 1 Installing

This document provides instructions on how to install the *RTI® Limited Bandwidth Endpoint Discovery (LBED) Plugin*.

After installation, please see the *RTI Limited Bandwidth Endpoint Discovery Plugin User's Manual* for an overview of the plugin's capabilities and configuration instructions.

Notes:

- These instructions use forward slashes (/) in directory paths. If you are on a Windows machine, use backwards slashes instead (\).
- NDDSHOME is described in [Chapter 2 Paths Mentioned in Documentation on page 3](#).
- You do not need root/administrator privileges.

1. Install *RTI Limited Bandwidth Endpoint Discovery Plugin* on top of *RTI Connexxt® DDS*:

Make sure you have a compatible version of *RTI Connexxt DDS*, as described in the *RTI Limited Bandwidth Endpoint Discovery Plugin Release Notes*.

Use the `<NDDSHOME>/bin/rtipkginstall` batch file to install *RTI Limited Bandwidth Endpoint Discovery Plugin*:

```
cd <NDDSHOME>  
bin/rtipkginstall <path to file>
```

2. Add `<NDDSHOME>/lib/<architecture>` to your **PATH** and **LD_LIBRARY_PATH** (on UNIX-based systems) or **Path** (on Windows systems) environment variable (replacing `<architecture>` with the appropriate string for your system architecture).

Architecture strings are listed in the *RTI Limited Bandwidth Endpoint Discovery Plugin Release Notes*.

For example, on a UNIX-based system:

```
>setenv PATH \  
  /home/your name/rti_connexrt_dds-6.x.y/lib/i86Linux3gcc4.8.2:$PATH  
> setenv LD_LIBRARY_PATH \  
  /home/your name/rti_connexrt_dds-6.x.y/lib/i86Linux3gcc4.8.2:${LD_LIBRARY_PATH}
```

For help with this process, see the *RTI Connexrt DDS Core Libraries Getting Started Guide*.

If you are using Visual Studio®: You must have an appropriate version of the Visual Studio Redistributable Package installed on the machine where you are *running* an application built with the dynamic libraries. For details, see the *RTI Connexrt DDS Core Libraries Platform Notes*.

Chapter 2 Paths Mentioned in Documentation

The documentation refers to:

- **<NDDSHOME>**

This refers to the installation directory for *RTI® Connex® DDS*. The default installation paths are:

- Mac® OS X® systems:
/Applications/rti_connex_dds-6.0.0
- UNIX-based systems, non-*root* user:
/home/<your user name>/rti_connex_dds-6.0.0
- UNIX-based systems, *root* user:
/opt/rti_connex_dds-6.0.0
- Windows® systems, user without Administrator privileges:
<your home directory>\rti_connex_dds-6.0.0
- Windows systems, user with Administrator privileges:
C:\Program Files\rti_connex_dds-6.0.0

You may also see \$NDDSHOME or %NDDSHOME%, which refers to an environment variable set to the installation path.

Wherever you see <NDDSHOME> used in a path, replace it with your installation path.

Note for Windows Users: When using a command prompt to enter a command that includes the path **C:\Program Files** (or any directory name that has a space), enclose the path in quotation marks. For example:

```
"C:\Program Files\rtdi_connext_dds-6.0.0\bin\rtiddsgen"
```

Or if you have defined the NDDSHOME environment variable:

```
"%NDDSHOME%\bin\rtiddsgen"
```

- **<path to examples>**

By default, examples are copied into your home directory the first time you run *RTI Launcher* or any script in **<NDDSHOME>/bin**. This document refers to the location of the copied examples as **<path to examples>**.

Wherever you see **<path to examples>**, replace it with the appropriate path.

Default path to the examples:

- Mac OS X systems: **/Users/<your user name>/rtdi_workspace/6.0.0/examples**
- UNIX-based systems: **/home/<your user name>/rtdi_workspace/6.0.0/examples**
- Windows systems: **<your Windows documents folder>\rtdi_workspace\6.0.0\examples**

Where 'your Windows documents folder' depends on your version of Windows. For example, on Windows 10, the folder is **C:\Users\<your user name>\Documents**.

Note: You can specify a different location for **rtdi_workspace**. You can also specify that you do not want the examples copied to the workspace. For details, see *Controlling Location for RTI Workspace and Copying of Examples* in the *RTI Connext DDS Core Libraries Getting Started Guide*.